

L'exemplaire filmé fut reproduit grâce à la générosité de:




Bibliothèque
Agriculture Canada

Les images suivantes ont été reproduites avec le plus grand soin, compte tenu de la condition et de la netteté de l'exemplaire filmé, et en conformité avec les conditions du contrat de filmage.

Les exemplaires originaux dont la couverture en papier est imprimée sont filmés en commençant par le premier plat et en terminant soit par la dernière page qui comporte une empreinte d'impression ou d'illustration, soit par le second plat, selon le cas. Tous les autres exemplaires originaux sont filmés en commençant par la première page qui comporte une empreinte d'impression ou d'illustration et en terminant par la dernière page qui comporte une telle empreinte.

Un des symboles suivants apparaîtra sur la dernière image de chaque microfiche, selon le cas: le symbole $\rightarrow$ signifie "A SUIVRE", le symbole ∇ signifie "FIN".

Les cartes, planches, tableaux, etc., peuvent être filmés à des taux de réduction différents. Lorsque le document est trop grand pour être reproduit en un seul cliché, il est filmé à partir de l'angle supérieur gauche, de gauche à droite, et de haut en bas, en prenant le nombre d'images nécessaire. Les diagrammes suivants illustrent la méthode.



PAMPHLET No. 19.

DOMINION OF CANADA.

DOMINION EXPERIMENTAL FARMS.

J. H. GRIDALE, B.Agr., D.Sc.A.,
Director.

W. T. MACOUN,
Dominion Horticulturist.

HOW TO MAKE AND USE HOTBEDS AND COLD FRAMES.

BY **W. T. MACOUN,**
Dominion Horticulturist.

A hotbed is desirable wherever vegetables or flowers are grown in Canada. It is a means by which plants are grown through their earlier stages in a suitable temperature in order to shorten the time of reaching condition for use or of coming into flower. It is the early vegetables which are the most profitable and most appreciated. Furthermore, with a hotbed it is possible to mature certain vegetables in parts of Canada where, if started in the open, they would not ripen before being killed by frost. Again, with a hotbed it is possible to mature a large crop when without one the crop would be very small. Certain vegetables also, even if not subjected to actual frost, will not grow if the soil and air are cold, hence must be started in warm soil and warm air such as is afforded by a hotbed, and the plants grown there are not set out in the open until warm weather has set in. Such crops as radish, lettuce, spinach, carrots and other vegetables which will reach marketable size in a relatively short season and are easily handled while the weather is still cool in early spring reach the stage when they are ready for use much sooner when kept in the hotbed or cold frame than if one had to wait until the seed were planted in the open and the plants developed there. There is usually greater danger from keeping the hotbed too hot for these particular vegetables than its being too cool. Cauliflower also can be grown to maturity in hotbeds, and in places where it is difficult owing to summer frosts or cool weather to grow cucumbers and melons, a few plants in a hotbed will provide a fair supply for the family.

MAKING THE HOTBED.

In making a hotbed, the first step is to choose a good situation on the south side of a building, wall or close board fence where the cold winds from the north will be broken and all the sunshine possible will be obtained. After deciding on the site, the frame should be made. The simplest frame is one made out of two-inch planks. It should be so constructed that it may be raised, as this may be necessary if the plants are too close to the glass. The frame should be at least six inches higher at the back than at the front, in order that the rain will run off readily and the plants get more sunshine.

The corners of the frame should be strengthened by dovetailing them and by using iron bands on the outside of the frame at the corners. If this is not done the frame is liable to sag. By cutting the ends of the end boards of the frames at an angle the right slope will be given the frame even though the boards are the same width on both sides. The inside of the frame should be about five feet eight inches wide, inside measurement, so that the six foot sash will rest nicely on the edges of the frame.

The sashes generally used are six by three feet. Where space is limited and it is desirable to remove the hotbed after one is done using it for the season, a frame made so that it can be taken apart readily and put together again easily may be used. A hotbed may be made either above or below ground. If above ground, it may be made in any situation where the water is not likely to lie. The one below ground is usually preferable if it can be made where the land is high and well drained. To make the latter, the soil should be taken out to the depth of about eighteen inches or more and about three feet wider than the frame so that there will be room for banking. The banking is a very important part of the construction of a hotbed as the conservation of heat in the bed depends very much upon it. It will be readily seen that much labour will be saved by doing the necessary excavation for the frame in the autumn when there is no frost in the ground. Horse manure is the best to use in making the hotbed and it should be quite fresh, not cold and rotten, and not already heated. It should be piled near where the hotbed is to be, and when it begins to heat it should be turned to make it of more uniform consistency. As the pile of manure required for a small hotbed will be small and the manure not heat so well on this account as if the pile had been larger, and as it will soon cool down in cold weather unless protected, it is desirable to cover it in some way. If the manure is very strawy it will not heat quickly and may be too hot later on. Five or six days after turning, it should be quite hot and is now ready for use. The bed is started from one end and the manure shaken in from a fork so that the long and short manure will be well mixed. When one layer is made it should be tramped well and then another layer started, and so on, tramping each layer well until the manure is the depth required. The depth will depend on when the bed is made. If made early, the manure should be from two to two and a half feet in depth, but if made during the latter part of March when the weather is not very cold, about a foot of manure will suffice. After the manure has been put in, the frame should be placed on and then about four to six inches more manure put in and banked well around the sides of the frame, both inside and out. Outside, the manure should be banked to the top of the frame and from twelve to fifteen inches in width. The bed is now ready for the sashes and the frames should be so constructed that they will fit snugly. Shelters made of one-inch lumber the same size as the sashes are useful for covering them, as they help to conserve the heat in cold weather. In two or three days the sash should be removed, the manure given a tramp all over, making it level where necessary, and then the soil put on. To get the best results the soil should be prepared the previous autumn and left in a pile over winter. It should be rich and of such a character that it will not bake. A good garden soil mixed with one-quarter to one-third its bulk of well rotted manure makes a good soil for hot-beds. Rotted sod also makes a very good soil. Some soils are very loose and where such have to be used they should be made firm with a board before the seed is sown, otherwise the seed will not germinate readily. The soil should be from five to six inches in depth over the manure, and it is better to have it a little deep than too shallow. The soil when it is put in should come near the top of the frame at the lower side as the manure will sink considerably, and the nearer the plants are to the glass later on the stockier they will be. In five or six days the hot-bed will be ready for the seed, but it is necessary to wait until the manure has cooled a little and the temperature has fallen to between 80 degrees and 90 degrees Fahrenheit. During this time when it is hottest, some of the heat may be allowed to escape by raising the sashes a little every day. One should have a metal thermometer for thrusting into the soil to determine the temperature.

Wooden thermometers warp with the heat.

SOWING THE SEED AND CARE OF THE PLANTS.

One should not be in a hurry to sow the seed, as if the temperature is too high the results will not be satisfactory. When the bed has reached the right temperature the soil should be spaded over a couple of times and the surface levelled and made

fine with the rake. The bed is now ready for sowing. The seed is usually sown in rows about four inches apart and about the same depth as outside. When the young plants come up, the frame should be kept sufficiently aired by raising the back or higher part of the sash to prevent the plants from getting spindly or weakly, when they are apt to damp off. Great care, however, should be taken when ventilating when the wind is high in cold weather as cold wind blowing directly on the plants will injure them. A board should be put at the end of the sash to break the force of the wind. In cold weather one may be tempted not to ventilate at all, when there may be such heat in the bed that, without ventilation, the plants will damp off, hence even a very little air is desirable, but if the bed is rather cold the temperature should not be lowered by admitting cold air. The temperature in the bed should not get below 50 degrees Fahrenheit nor should it be above 85 degrees. Flats or boxes 12 by 18 inches in size containing three to four inches of soil are convenient for handling the plants. There should be thorough drainage in the flats or boxes which can be obtained by boring about five half-inch holes in the bottoms. Where these are used, it is not necessary to put much soil over the manure, the flats or boxes being set in the frame. Sometimes if the manure is too hot the roots of the plants are injured in the flats and if there is danger of this they should be set on laths to leave an air space between the flat and the manure. Care should be taken to prevent the plants being chilled or frozen. The soil must be watered when necessary, but it is best to have the surface of the soil rather dry than wet, as damping off is much more likely to occur when the surface is wet. As soon as the plants are large enough they are pricked out into another frame.

If plants get so large that they reach the glass, the frame should be raised, which can be done by putting a block of wood at each corner. As the foliage of plants grown in hotbeds is very tender, if the plants are put outside before exposing them for a few days without glass in the hotbed to harden off, they are very likely to be injured by the sun and by the wind, and will be more likely to be affected by light frosts if there should be such. It is, therefore, important to harden off plants before setting them out, otherwise all the advantage of the hotbed may be lost.

COLD FRAME.

A cold frame is much like a hotbed in appearance, but is without manure. It is used either for growing plants taken from the hotbed before they can be set out in the open, or it may also be used by those who start plants in the house and who cannot or do not wish to use manure.

A well chosen place is chosen in the autumn and rich, friable soil, six inches or more in depth, is put where the frame is to be placed. This soil and the ground about should be protected from frost by leaves or litter, which should not contain weed seeds. By thus mulching the soil in the autumn, when the time comes for planting in the spring there will be no frost in the ground about the frame. A frame should now be made with sides and ends of twelve-inch boards, preferably two inches in thickness and placed on a slope so that the back part of the frame is six inches higher than the front. The frame is now placed over the soil. As hotbed sashes are six by three feet in size, the frame should be made to accommodate one or more of them. The soil is now well spaded and the frame protected from frost by earthing up outside or banking with manure. If the glass sash is over the top a few days before it is time to sow or set out the plants, the soil will be warmed up sufficiently. Cotton is sometimes used for covering cold frames instead of glass, and quite satisfactory results are obtained, but where late severe frosts are liable to occur glass is safer. Plants should not be taken out of the house and planted in cold soil or they will be chilled and injured. The same attention in regard to watering and ventilation should be given to the cold frame as to the hotbed. By the use of a cold frame, plants will be well advanced when it is time to set them out and several weeks will be saved.



Outside View of Hotbed.



Sectional View of Hotbed.



